

# Elements of Reality

Frank Rioux  
Emeritus Professor of Chemistry  
CSB | SJU

In the '90s N. David Mermin published two articles in the general physics literature (*Physics Today*, June 1990; *American Journal of Physics*, August 1990) on the Greenberger-Horne-Zeilinger (GHZ) gedanken experiment (*American Journal of Physics*, December 1990; *Nature*, 3 February 2000) involving three spin-1/2 particles that illustrated the clash between local realism and the quantum view of reality for the quantum nonspecialist.

The three spin-1/2 particles are created in a single event and move apart in the horizontal y-z plane. It will be shown that a consideration of spin measurements (in units of  $h/4\pi$ ) in the x- and y-directions reveals the impossibility of assigning values to the spin observables independent of measurement.

The x- and y-direction spin operators are the Pauli matrices:  $\sigma_x := \begin{pmatrix} 0 & 1 \\ 1 & 0 \end{pmatrix}$      $\sigma_y := \begin{pmatrix} 0 & -i \\ i & 0 \end{pmatrix}$

The eigenvalues of the Pauli matrices are +/- 1:     $\text{eigenvals}(\sigma_x) = \begin{pmatrix} 1 \\ -1 \end{pmatrix}$      $\text{eigenvals}(\sigma_y) = \begin{pmatrix} 1 \\ -1 \end{pmatrix}$

The following operators represent the measurement protocols for spins 1, 2 and 3.

$$\sigma_x^1 \otimes \sigma_y^2 \otimes \sigma_y^3 \quad \sigma_y^1 \otimes \sigma_x^2 \otimes \sigma_y^3 \quad \sigma_y^1 \otimes \sigma_y^2 \otimes \sigma_x^3 \quad \sigma_x^1 \otimes \sigma_x^2 \otimes \sigma_x^3$$

The tensor matrix product, also known as the Kronecker product, is available in Mathcad. The four operators in tensor format are formed as follows.

$$\begin{aligned} \sigma_{xyy} &:= \text{kroncker}(\sigma_x, \text{kroncker}(\sigma_y, \sigma_y)) & \sigma_{yxy} &:= \text{kroncker}(\sigma_y, \text{kroncker}(\sigma_x, \sigma_y)) \\ \sigma_{yyx} &:= \text{kroncker}(\sigma_y, \text{kroncker}(\sigma_y, \sigma_x)) & \sigma_{xxx} &:= \text{kroncker}(\sigma_x, \text{kroncker}(\sigma_x, \sigma_x)) \end{aligned}$$

These operators mutually commute, meaning that they can be assigned simultaneous eigenstates with simultaneous eigenvalues.

$$\sigma_{xyy} \cdot \sigma_{yxy} - \sigma_{yxy} \cdot \sigma_{xyy} \rightarrow 0 \quad \sigma_{xyy} \cdot \sigma_{yyx} - \sigma_{yyx} \cdot \sigma_{xyy} \rightarrow 0 \quad \sigma_{xyy} \cdot \sigma_{xxx} - \sigma_{xxx} \cdot \sigma_{xyy} \rightarrow 0$$

$$\sigma_{yxy} \cdot \sigma_{yyx} - \sigma_{yyx} \cdot \sigma_{yxy} \rightarrow 0 \quad \sigma_{yxy} \cdot \sigma_{xxx} - \sigma_{xxx} \cdot \sigma_{yxy} \rightarrow 0 \quad \sigma_{yyx} \cdot \sigma_{xxx} - \sigma_{xxx} \cdot \sigma_{yyx} \rightarrow 0$$

The next step is to compare the matrix for the product of the first three operators ( $\sigma_{xyy} \cdot \sigma_{yxy} \cdot \sigma_{yyx}$ ) with that of the fourth ( $\sigma_{xxx}$ ).

$$\sigma_{xyy} \cdot \sigma_{yxy} \cdot \sigma_{yyx} = \begin{pmatrix} 0 & 0 & 0 & 0 & 0 & 0 & 0 & -1 \\ 0 & 0 & 0 & 0 & 0 & 0 & -1 & 0 \\ 0 & 0 & 0 & 0 & 0 & -1 & 0 & 0 \\ 0 & 0 & 0 & 0 & -1 & 0 & 0 & 0 \\ 0 & 0 & 0 & -1 & 0 & 0 & 0 & 0 \\ 0 & 0 & -1 & 0 & 0 & 0 & 0 & 0 \\ 0 & -1 & 0 & 0 & 0 & 0 & 0 & 0 \\ -1 & 0 & 0 & 0 & 0 & 0 & 0 & 0 \end{pmatrix} \quad \sigma_{xxx} = \begin{pmatrix} 0 & 0 & 0 & 0 & 0 & 0 & 0 & 1 \\ 0 & 0 & 0 & 0 & 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 0 & 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 0 & 1 & 0 & 0 & 0 \\ 0 & 0 & 0 & 1 & 0 & 0 & 0 & 0 \\ 0 & 0 & 1 & 0 & 0 & 0 & 0 & 0 \\ 0 & 1 & 0 & 0 & 0 & 0 & 0 & 0 \\ 1 & 0 & 0 & 0 & 0 & 0 & 0 & 0 \end{pmatrix}$$

This indicates the following relationship between the four operators and leads quickly to a refutation of the concept of noncontextual, hidden values for quantum mechanical observables.

$$(\sigma_x^1 \otimes \sigma_y^2 \otimes \sigma_y^3)(\sigma_y^1 \otimes \sigma_x^2 \otimes \sigma_y^3)(\sigma_y^1 \otimes \sigma_y^2 \otimes \sigma_x^3) = -(\sigma_x^1 \otimes \sigma_x^2 \otimes \sigma_x^3)$$

Local realism assumes that objects have definite properties independent of measurement. In this example it assumes that the x- and y-components of the spin have definite values prior to measurement. This position leads to a contradiction with the above result. There is no way to assign eigenvalues (+/-1) to the operators that is consistent with the above result.

Concentrating on the operator on the left side, we notice that there is a  $\sigma_y$  measurement on the first spin in the second and third term (blue). If the spin state is well-defined before measurement those results have to be the same, either both +1 or both -1, so that the product of the two measurements is +1. There is a  $\sigma_y$  measurement on the second spin in terms one and three (red). By similar arguments those results will lead to a product of +1 also. Finally there is a  $\sigma_y$  measurement on the third spin in terms one and two (green). By similar arguments those results will lead to a product of +1 also. Incorporating these observations into the expression above leads to the following contradiction.

$$\sigma_x^1 \otimes \sigma_x^2 \otimes \sigma_x^3 = -\sigma_x^1 \otimes \sigma_x^2 \otimes \sigma_x^3$$

This result should cause all mathematically literate local realists to renounce and recant their heresy.

### Appendix

It is now shown that the eigenfunctions of the measurement operators are the GHZ eigenstates.

$$\text{eigenvecs}(\sigma_{xxx}) = \begin{pmatrix} 0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & -0.707 \\ 0 & 0 & 0.707 & 0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & -0.707 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & 0.707 & 0 & 0 \\ 0 & 0 & 0.707 & -0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & 0.707 \\ 0.707 & -0.707 & 0 & 0 & 0 & 0 & 0 & 0 \end{pmatrix} \quad \text{eigenvals}(\sigma_{xxx}) = \begin{pmatrix} 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \end{pmatrix}$$

$$\text{eigenvecs}(\sigma_{xyy}) = \begin{pmatrix} 0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & 0.707 \\ 0 & 0 & 0.707 & 0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & -0.707 & -0.707 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & -0.707 & 0 & 0 \\ 0 & 0 & 0.707 & -0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & -0.707 \\ -0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \end{pmatrix} \quad \text{eigenvals}(\sigma_{xyy}) = \begin{pmatrix} 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \end{pmatrix}$$

$$\text{eigenvecs}(\sigma_{yxy}) = \begin{pmatrix} 0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & 0.707 \\ 0 & 0 & 0.707 & 0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & 0.707 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & -0.707 & 0 & 0 \\ 0 & 0 & -0.707 & 0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & -0.707 \\ -0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \end{pmatrix} \quad \text{eigenvals}(\sigma_{yxy}) = \begin{pmatrix} 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \end{pmatrix}$$

$$\text{eigenvecs}(\sigma_{yyx}) = \begin{pmatrix} 0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & -0.707 & 0.707 \\ 0 & 0 & 0.707 & 0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & -0.707 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0.707 & 0.707 & 0 & 0 \\ 0 & 0 & 0.707 & -0.707 & 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 & 0 & 0 & 0.707 & 0.707 \\ -0.707 & 0.707 & 0 & 0 & 0 & 0 & 0 & 0 \end{pmatrix} \quad \text{eigenvals}(\sigma_{yyx}) = \begin{pmatrix} 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \\ 1 \\ -1 \end{pmatrix}$$

Using any of the GHZ eigenvectors to calculate the expectation values of the measurement operators satisfies the following relation.

$$(\sigma_x^1 \otimes \sigma_y^2 \otimes \sigma_y^3)(\sigma_y^1 \otimes \sigma_x^2 \otimes \sigma_y^3)(\sigma_y^1 \otimes \sigma_y^2 \otimes \sigma_x^3) = -(\sigma_x^1 \otimes \sigma_x^2 \otimes \sigma_x^3)$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (1 \ 0 \ 0 \ 0 \ 0 \ 0 \ 0 \ 1)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = 1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (1 \ 0 \ 0 \ 0 \ 0 \ 0 \ 0 \ -1)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = -1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (0 \ 1 \ 0 \ 0 \ 0 \ 0 \ 1 \ 0)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = 1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (0 \ 1 \ 0 \ 0 \ 0 \ 0 \ -1 \ 0)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = -1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (0 \ 0 \ 1 \ 0 \ 0 \ 1 \ 0 \ 0)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = 1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (0 \ 0 \ 1 \ 0 \ 0 \ -1 \ 0 \ 0)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = -1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (0 \ 0 \ 0 \ 1 \ 1 \ 0 \ 0 \ 0)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = 1$$

$$\Psi := \frac{1}{\sqrt{2}} \cdot (0 \ 0 \ 0 \ 1 \ -1 \ 0 \ 0 \ 0)^T$$

$$\Psi^T \cdot \sigma_{xyy} \cdot \Psi = 1 \quad \Psi^T \cdot \sigma_{yxy} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{yyx} \cdot \Psi = -1 \quad \Psi^T \cdot \sigma_{xxx} \cdot \Psi = -1$$